

- ▶ Quick Internet Setup
- ▶ Network
- ▶ Internet Services
- ▶ Advanced Setting
- ▶ Administration
- ▶ Diagnostic
- ▶ Router Status

Wireless
LAN
WAN

WAN
ATM Settings
ADSL Setting

VPI: VCI: Encapsulation: LLC VC-Mux
 Channel Mode: Enable NAPT:
 Enable IGMP:

PPP Settings:
 User Name: Password:
 Type: Idle Time (min):

WAN IP Settings:
 Type: Fixed IP DHCP
 Local IP Address: Remote IP Address:
 Netmask:
 Default Route: Disable Enable Auto
 Unnumbered

-

NEXT

Current ATM VC Table:

Select	Inf	Mode	VPI	VCI	Encap	NAPT	IGMP	DRoute	IP Addr	Remote IP	NetMask	User Name	Unnumber	Status	Edit
<input type="radio"/>	pppoe1	PPPoE	0	32	LLC	On	Off	Off	0.0.0.0	0.0.0.0	255.255.255.255	tw	---	down	

Protocol:	PPPoE
ATM VCC:	0/32
Login Name:	<input type="text" value="tw"/>
Password:	<input type="password" value="••"/>
Authentication Method:	<input type="text" value="Auto"/>
Connection Type:	<input type="text" value="Continuous"/>
Idle Time (s):	<input type="text" value="0"/>
Bridge:	<input type="radio"/> Bridged Ethernet (Transparent Bridging) <input type="radio"/> Bridged PPPoE (implies Bridged Ethernet) <input checked="" type="radio"/> Disable Bridge
AC-Name:	<input type="text"/>
Service-Name:	<input type="text"/>
802.1q:	<input checked="" type="radio"/> Disable <input type="radio"/> Enable
MTU (576-1500):	VLAN ID(1-4095): <input type="text" value="0"/> <input type="text" value="1400"/>
Static IP:	<input type="text"/>
Source Mac address:	<input type="text" value="00:05:1D:03:04:05"/> (ex:00:E0:86:71:05:02) <input type="button" value="MACCLONE"/>

الرئيسية

System

LAN

Wireless

WAN

Port Mapping

Statistics

ARP Table

Statistics

ADSL
Statistics

This page shows the setting of the ADSL Router.

ADSL Line Status	SHOWTIME.L0
ADSL Mode	G992.5
Up Stream	1144 kbps
Down Stream	18767 kbps
Attenuation Down Stream(db)	21
Attenuation Up Stream(db)	14
SNR Margin Down Stream(db)	6.2
SNR Margin Up Stream(db)	5.7
Attainable Down Rate	21084 kbps
Attainable Up Rate	1144 kbps
Vendor ID	RETK
Firmware Version	2920bc12
CRC Errors	21
Up Stream BER	28132e-7
Down Stream BER	0e-7
Up Output Power	12.5
Down Output Power	18.5
Down Stream ES	49
Up Stream ES	4294967295
Down Stream SES	30
Up Stream SES	0
Down Stream UAS	195
Up Stream UAS	4294966846

الرئيسية

▶ Quick Internet Setup

▶ Network

▶ Internet Services

▶ Advanced Setting

▶ Administration

▶ Diagnostic

▶ Router Status

▶ Quick Internet Setup

▶ Network

▶ Internet Services

▶ Advanced Setting

▶ Administration

▶ Diagnostic

▶ Router Status

Quick Internet Setup**Wizard**

The Wizard page guides you to configure the device step by step. After finishing the following steps, you will be online and free to enjoy high-speed Internet access.

Step 1: Web Account Setup

Step 2: Time Zone Setup

Step 3: WAN Interface Setup

Step 4: WLAN Interface Setup

Step 5: Configuration Saving

Step 1: Web Account Setup

Set a new account for accessing the Web server of the device.

User Name:

admin ▾

New Password:

●●●●

(MaxLength: 15)

Confirmed Password:

●●●●

(MaxLength: 15)

NEXT

Next >

Quick Internet Setup

▶ Quick Internet Setup

▶ Network

▶ Internet Services

▶ Advanced Setting

▶ Administration

▶ Diagnostic

▶ Router Status

Step 2: Time Zone Setup

Set up the system time and the Network Time Protocol (NTP) server.

NTP Configuration:

State: Disable Enable

NTP Server: pool.ntp.org

Interval: Every 1 hours

Time Zone: (GMT) Gambia, Liberia, Morocco, England ▾

GMT time: Thu Jan 1 0:3:57 1970

< Back

Next >

NEXT

Quick Internet Setup

▶ Quick Internet Setup

▶ Network

▶ Internet Services

▶ Advanced Setting

▶ Administration

▶ Diagnostic

▶ Router Status

Step 1: The Internet Setup

This page allows you to configure the ADSL settings. A predefined list of countries & Internet Service Providers (ISP) is available for easy configuration.

(1). Select Country.

(2). Select ISP.

Note: If Country or ISP is not listed select Other. You will be required to manually select the Protocol & fill in blank fields. For correct values contact your ISP.

(3). Enter required values.

(4). Click Next to continue

Country	Serbia	notlisted
Internet Service Provider	Others	notlisted
Protocol	PPPoE	▾
Connection Type	LLC	▾
VPI	8	(0-255)
VCI	35	(32-65535)
Username@aya.sy	
Password	*****	
Confirm Password	*****	

NEXT

Back

Next

Quick Internet Setup

▶ Quick Internet Setup

▶ Network

▶ Internet Services

▶ Advanced Setting

▶ Administration

▶ Diagnostic

▶ Router Status

Step 4: WLAN Interface Setup

Set up the parameters of WLAN interface.

WLAN Interface:

Enable Disable

Band:

2.4 GHz(B+G+N) ▾

SSID:

ASUS

Encryption:

None

None

WEP

WPA (TKIP)

WPA (AES)

WPA2(AES)

WPA2(TKIP)

WPA/WPA2

< Back

Next >

ثم نضع كلمة المرور في
المربع الخاص ثم

NEXT

Quick Internet Setup

▶ Quick Internet Setup

▶ Network

▶ Internet Services

▶ Advanced Setting

▶ Administration

▶ Diagnostic

▶ Router Status

Step 5: Configuration Saving

Click "Finish" to save the settings. Click "Back" to make more modifications. Click "Reset" to cancel the settings.

The parameters you set:

User Name:	admin
Password:	admin
NTP State:	Enable
NTP Server:	pool.ntp.org
NTP Interval:	1
Time Zone:	1
VPI:	8
VCI:	35
Encapsulation:	LLC/SNAP
Channel Mode:	pppoe
PPP User Name:	111764633@pttnet
PPP Password:	111764633
DNS Setting:	Obtain DNS Automatically
WLAN Interface:	Enable

< Back

Finish

Reset

الرئيسية